

# MiVRy QuestHands

## 3D Gesture Recognition AI for Oculus Quest Hand Tracking

V2.10



©2024 MARUI-PlugIn (inc.)

# MiVRy QuestHands: 3D GESTURE RECOGNITION PLUG-IN FOR UNITY

Copyright (c) 2024 MARUI-PlugIn (inc.)

**[IMPORTANT!]** This license is for the use of the MiVRy Gesture Recognition plug-in (.dll and .so files as well as the source code) and does not include the use of the asset files used in the sample scenes (3d models and textures etc.)

Please see the license statement at the end of this document.

Check out our YouTube channel for tutorials, demos, and news updates:

<https://www.youtube.com/playlist?list=PLYt4XosVICmWtmDmx1IS8OVGU70tmQOfv>

## Content:

- 1: [What is 3D Gesture Recognition](#)
- 2: [Quick Start Guide](#)
- 3: [Package Overview](#)
- 4: [License and Activation](#)
- 5: [How to use the GestureManager](#)
- 6: [How to use the MiVRy gesture recognition object](#)
- 7: [How to use the GestureRecognition script \(for one-handed gestures\)](#)
- 8: [How to use the GestureCombinations script \(for two-handed gestures or gesture combos\)](#)
- 9: [How to use MiVRy with Bolt visual programming graphs](#)
- 10: [Build instructions for Windows](#)
- 11: [Build instructions for Android \(Mobile VR, Oculus Quest, ...\)](#)
- 12: [Troubleshooting and Frequently Asked Questions \(FAQ\)](#)
- 13: [Software license statement \(EULA\)](#)

## 1: What is 3D Gesture Recognition?

Making good user interaction for VR is hard. The number of buttons often isn't enough and memorizing button combinations is challenging for users.

Gestures are a great solution! Allow your users to wave their 3D controllers like a magic wand and have wonderful things happen. Draw an arrow to shoot a magic missile, make a spiral to summon a hurricane, shake your controller to reload your gun, or just swipe left and right to "undo" or "redo" previous operations.

MARUI (inc.) has many years of experience of creating VR/AR/XR user interfaces for 3D design software.

Now YOU can use its powerful gesture recognition module in Unity.

This is a highly advanced artificial intelligence that can learn to understand your 3D controller motions.

The gestures can be both direction specific ("swipe left" vs. "swipe right") or direction independent ("draw an arrow facing in any direction") - either way, you will receive the direction, position, and scale at which the user performed the gesture.

Draw a large 3d cube and there it will appear, with the appropriate scale and orientation.

Both one-handed and two-handed gestures are supported and you can even build combos of sequential gestures.

### **Key features:**

- Real 3D gestures - like waving a magic wand in all three dimensions
- Support for multi-part gesture combinations such as two-handed gestures or sequential combinations of gestures
- Record your own gestures - simple and straightforward
- Easy to use C# classes and convenient wrapper objects
- Can have multiple sets of gestures simultaneously (for example: different sets of gestures for different buttons)
- High recognition fidelity
- Outputs the position, scale, and orientation at which the gesture was performed
- High performance (back-end written in optimized C/C++)
- Includes a Unity sample scenes that illustrate how to use the plug-in
- Save gestures to file for later loading
- Support for Windows, Android-based devices (Oculus Quest, Smartphones, ...), UWP devices (Hololens), and Linux

## 2: Quick Start Guide:

This guide explains the simplest way to use MiVRy Quest Hands in your Unity project. Necessarily, a lot of features are not fully explained here. Please read the rest of this document for more details and additional explanations of features.

### 2.1: Use the MivryQuestHands Gesture Manager to record your gestures:

Either open the GestureManager scene in the GestureManager/ folder in Unity or download a pre-built version of the MivryQuestHands GestureManager from <https://www.marui-plugin.com/documentation-mivry-questhands/#gesturemanager>

A video tutorial on how to use the MivryQuestHands GestureManager is available on YouTube: <https://www.youtube.com/watch?v=gZwkGgoCDpM>

When you are happy with your recorded gestures, save the recorded gestures to a Gesture Database File (.dat file).

### 2.2: Import the plug-in library files and script files into your project:

To use MivryQuestHands in your own project, you need to import the plug-in library files (.dll and/or .so files) as well as the script files (MivryQuestHands.cs, GestureRecognition.cs, and GestureCombinations.cs).

You can do so either by importing the MivryQuestHands Unity package (either through the Unity PackageManager or from the title bar “Assets” -> “Import Package” -> “Custom Package”) or by manually copying the files. The package and individual files are also available on our GitHub page: <https://github.com/MARUI-Plugin/MiVRy/>

#### 2.2.A: Importing the MivryQuestHands Unity Package:

You can get the MiVRy Unity Package either on the Unity Asset Store ( <https://assetstore.unity.com/packages/slug/239214> ) or from Github (<https://github.com/MARUI-Plugin/MiVRy/blob/master/unity/MiVRyQuestHands.unitypackage> ).

When you get the MiVRy package through the asset store, you can add it to your project via the Unity Package Manager (in the title bar “Window” -> “Package Manager”).

If you download the package from Github, import it by selecting “Assets” -> “Import Package” -> “Custom Package” on the title bar.


The package also contains the source code to the GestureManager and several samples. These are not required and are optional.

To use MiVRy, you only need to select the “Plugins/” folder and the *MivryQuestHands.cs*, *GestureRecognition.cs*, and *GestureCombinations.cs* script files.

## 2.2.B: Manually import the library files and script files:

Alternatively, to importing the package, you can manually copy the required files into your project. Copy the *.dll* and *.so* files from the *Plugins/* folder into your own project's *Plugins/* folder. (If your project does not yet have a *Plugins/* folder just create a now folder named "Plugins").

Select the files in Unity and in the inspector ensure that they are selected as plug-ins for the respective architecture:




Then copy the *MivryQuestHands.cs*, *GestureRecognition.cs* and *GestureCombinations.cs* files into your own project (for example into your *Scripts/* folder).

## 2.3: Add MivryQuestHands component to your scene:

Select a GameObject in your scene (or create a new GameObject) and use the "Add Component" button in the Inspector to attach the MivryQuestHands component to it.

In the Inspector, set the properties of the MivryQuestHands component to comply with your project.



- The “License Name” and “License Key” fields can be left empty. Mivry is free to use for commercial and non-commercial projects. However, without a license Mivry is limited to 100 gesture recognitions (or 100 seconds of continuous gesture recognition).
- Set the “Gesture Database File” to the relative path where you stored the “.DAT” file created with the MivryQuestHands GestureManager. If you want to deploy your app to the Oculus Quest, it is advisable to place your .DAT file in the StreamingAssets/ folder and set the path relative inside that folder.
- The “Tracked Hand” field decides whether the left hand, right hand, or both hands are used for gesturing. However, if you use .DAT files created with the gesture manager, this information will also be read from the file and you don’t have to change it.
- The “Left Hand” and “Right Hand” must be set to the OVRHandPrefab for the left and right hand respectively. If your scene does not yet contain these prefabs, please see the official Oculus documentation on how to add Oculus Quest hand tracking to your Unity app:  
<https://developer.oculus.com/documentation/unity/unity-handtracking/>
- The “Left Hand Tracking Points” and “Right Hand Tracking Points” decide which bones in each hand are used for gesture recognition. Again, if you used the GestureManager to create your DAT file, you do not have to set this as it is saved inside the file.
- The “Left Hand Trigger” and “Right Hand Trigger” sets how you intend to signal that a gesture motion started or ended. For example, you can set the Left Hand Trigger to “making a pinch on the right hand”. Now, when you make a pinching motion on the right hand, Mivry will start tracking your left hand to detect a gesture. When you release the pinch, Mivry will stop the tracking and try to identify the gesture you just performed. You can set this to “Manual” to control the start and end of a gesture motion via script by setting the “Left Gesture Trigger Value” and “Right Gesture Trigger Value”. The “Left/Right Gesture Trigger Threshold” field decides what value (from 0 to 1) will be considered “gesturing” or “not-gesturing”.
- The “On Gesture Completion” event allows you to set up script functions to be called when a gesture was identified. Add a function to one of your scripts that takes a *GestureCompletionData* object as parameter:

```
public void OnGestureCompleted(GestureCompletionData data) {
    if (data.gestureID == 123) {
        ...
    }
}
```

Then set this function as the “On Gesture Completion” event in the Mivry component.

Now when you run your project, perform the “Trigger” and make a gesture motion, your *OnGestureCompleted* function will be called with details about the performed and identified gesture.


### 3: Package Overview:

#### (1) Plug-in library files (binaries):

In the Assets/GestureRecognition/Plugins/ folder you can find the plugin library files for various platforms:

- Plugins/x86/gesturerecognition.dll : plug-in library file for 32bit Windows apps
- Plugins/x86\_64/gesturerecognition.dll : plug-in library file for 64bit Windows apps
- Plugins/Android/arm64-v8a/libgesturerecognition.so : plug-in library for ARM64 Android apps
- Plugins/Android/armabi-v7a/libgesturerecognition.so : plug-in library for ARM v7 Android apps

To use the plug-in in your own project, place these files (or at least the file related to the architecture that you're developing for) in your Unity project under /Assets/Plugins/ and set the Import Settings in the Inspector to make Unity load the file for the correct platform:



#### (2) Plug-in wrapper scripts (C#)

MiVRy provides three different script to use the plug-in library. You ever only need *one* of the three, depending on your requirements and development goals.

- GestureRecognition.cs : C# script for using one-handed one-part gestures.
- GestureCombinations.cs: C# script for using two-handed or multi-part gestures.
- MivryQuestHands.cs : Unity component for simple use of pre-recorded gestures without coding.

To use MiVRy in your own project, include these files in your Unity project (for examples under /Assets/ Scripts/).

The *GestureRecognition.cs* and *GestureCombinations.cs* scripts are pure C# scripts and not Unity components. They allow you to use MiVRy via C# scripting in your own scripts and give the

greatest amount of flexibility. However, they are also more complex to use and require scripting. The *MivryQuestHands.cs* script is a Unity component script that can just be attached to any GameObject in Unity and allows you to use pre-recorded gestures without the need for scripting. However, it is also more limited.

Here is a simple chart to decide which of the scripts to use in your project:

	<b>GestureRecognition.cs</b>	<b>GestureCombinations.cs</b>	<b>Mivry.cs</b>
<i>How to use:</i>	C# scripting	C# scripting	Unity Inspector (no scripting required)
<i>Use pre-recorded gesture files:</i>	Yes	Yes	Yes
<i>Record new gestures:</i>	Yes	Yes	No (use GestureManager)

### **(3) GestureManager:**

In the *GestureManager/* folder, you will find a Unity Scene that allows easy recording and management of gesture database files (".dat" files) without any coding or development. You can also get a pre-built version of the Gesture Manager at <https://www.marui-plugin.com/documentation-mivry-unity/#gesturemanager>

You can use the GestureManager to record your own gestures.

### **(4) Sample:**

The Samples/ folder offers a Unity scene and scripts that illustrate how to use MivryQuestHands.

**[IMPORTANT]** The samples include several assets (3d models, prefabs, textures, ...). The MiVRy license does NOT include these assets! They are only included as part of the samples. You may NOT use any of the items in the *Resources* folder in your project.



## 4: License and Activation

MiVRy is free to use for commercial, personal, and academic use.

However, the free version of MiVRy has certain limitations.

The free version of MiVRy can only be used to identify 100 gestures per session (meaning every time you run the app). When using continuous gesture identification, it can only be used for a total of 100 seconds of identifying gestures.

To unlock unlimited gesture recognition, you must purchase a license at:

<https://www.marui-plugin.com/mivry/>

The license key will be sent to you automatically and immediately after purchase.

If the license email does not arrive, please check your spam filter, and contact [support@marui-plugin.com](mailto:support@marui-plugin.com)

The license credentials must then be used to activate MiVRy.

This activation is local – no internet connection is required and no data is transmitted.

If you're using the MiVRy component, you can just insert the license name and license key in the Unity Inspector of the component.

If you're using the GestureRecognition.cs or GestureCombinations.cs scripts, you must activate the object by using the `activateLicense()` function (during runtime).

### Using a License File:

Alternatively, you can save the license name (ID) and key into a file and load it with the `activateLicenseFile()` function or input the path to the license file into the Mivry.cs component if you use it.

The license file is a simple text file that you can create with any text editor, that contains the keywords "NAME" and "KEY", each followed by a colon (":") or equal sign ("=") and then your respective license credentials.

Here is an example of how the contents of a valid license file may look:

```
NAME: your@email.com_3z0UvQ3GBkAc74VW9nQKPlbm  
KEY : b701b7235a483698e61a2b8d69479ed013a03069fcb9b892302277a0f394c257
```

## 5: How to use the GestureManager

There are two ways to use the GestureManager: in the Unity Inspector and in VR.

### Using the GestureManager in the Unity Inspector:

The GestureManager.cs script can be attached as a component to any Unity GameObject. In the GestureManager scene, it is attached to the GameObject called “GestureManager”. You do not need to run the scene in order to use the GestureManager in the Inspector. Simply select the GestureManager GameObject (the Unity game object which has the GestureManager.cs script attached to it) and adjust the properties in the Inspector. However, in order to record new gestures, you obviously need to run the scene. Please note that starting/stopping will reset what you entered in the Inspector.

### Using the GestureManager in VR:

When you run the GestureManager scene (either inside the Unity Editor or stand-alone on any device, a floating panel will appear.

You can move the panel by pinching the blue handle bars on either side (index-finger-to-thumb-pinch).

A video tutorial on how to use the GestureManager in VR is available on YouTube:

<https://www.youtube.com/watch?v=gZwkGgoCDpM>

### Important input fields in the GestureManager (both Inspector and VR versions):

*Left Hand Tracking Points / Right Hand Tracking Points:* Which bones in each hand are considered to identify the gesture motion.

*Load Gesture File:* Load a previously recorded Gesture Database File (.DAT file), overwriting the current content of the Gesture Manager.

*Import Gesture File:* Add the gestures of a previously recorded Gesture Database File (.DAT file), while maintaining the current content of the Gesture Manager.

*Save Gesture File:* Save the current gestures to file.

*Frame of Reference:* Which coordinate system the gestures are encoded in. “Head” means gestures are interpreted as to how you see them through the VR headset, with “forward” pointing away from you no matter where you face in your room. “World” means gestures are interpreted in regard to their real-world position, with “north” being north even when you turn around to face another direction. “Hands” means that the motion of the fingers is only interpreted relative to the wrist, ignoring where in the world the hand is making the motion.

*Compensate head motion during gesture:* Whether the motion of your frame of reference should be removed from the motion of the joints of the hands. For example, if you’re turning your head to the right while constantly holding your hand in front of your face, the head rotation will be

compensated and your hand will appear motionless to the gesture recognition AI. Note that this can lead to identification problems, since many players are in the habit of continuously looking at their hands while gesturing. Then, this setting would remove all motion from the gesture, making it hard to identify.

*Record Gesture Samples:* This selects I for which gesture you want to record new samples or if you want to test the identification instead (please note that new samples do not have any effect until the “training” was performed). When you record samples, please make sure that you record the gesture many different ways. For example, if the player should be allowed to perform the gesture with a small motion and a large motion, be sure to record both small and large samples. It can also help to record gesture samples from several people to ensure that particular habits of one person don’t affect the recognition for other players.

*Coordinate System Conversion:* These two settings help to ensure that the same VR coordinates (the directions of “x”, “y”, and “z” of the headset and controllers) are used by the Gesture Manager and your final project. Set “Unity XR Plug-in” to the XR plug-in that you are using in Unity (in Unity Project Settings -> XR Plug-in Management). Set “MiVRy Coordinate System” to whichever coordinate system you want to use in your own project (for example: “Unreal” for Unreal Engine coordinates). If you don’t wish to use different coordinate systems, you don’t need to adjust these values.

*Start Training / Stop Training:* This starts or interrupts the training process where the AI tries to learn your gestures. The “Performance” value which is updated during the training indicates how many of your gestures the AI can already correctly identify. Even when the training is stopped prematurely the result is still preserved, so you can stop it as soon as you are satisfied. Sometimes the AI ‘misunderstands’ your intentions and the future recognition of gestures is not satisfactory. In this case, just re-run the training process. If the result still is not good, please record more gesture samples with greater variation to make it clearer to the AI what you intend.

## 6: How to use the MivryQuestHands gesture recognition component

(1) Add the MivryQuestHands.cs script as a component to one (any) object in your scene.

(2) In one of your own scripts, add a new function to handle the event when a gesture is performed and recognized. The function should have a parameter of the type GestureCompletionData and return type void.

Example:

```
public void OnGestureCompleted(GestureCompletionData data) {  
    if (data.gestureID == 123) {  
        ...  
    }  
}
```

(3) In the inspector, set the fields of the MivryQuestHands script component:

- "GestureDatabaseFile":

The path to the gesture recognition database file to load.

In the editor, this will be relative to the Assets/ folder.

In stand-alone (build), this will be relative to the StreamingAssets/ folder.

- "LeftHand" / "RightHand":

The OculusIntegration OvrHandPrefab game objects. If your scene does not yet contain these prefabs, please see the official Oculus documentation on how to add Oculus Quest hand tracking to your Unity app: <https://developer.oculus.com/documentation/unity/unity-handtracking/>

- "Left Hand Trigger" / "Right Hand Trigger":

How you intend to signal that a gesture motion started or ended. For example, you can set the Left Hand Trigger to "making a pinch on the right hand". Now, when you make a pinching motion on the right hand, Mivry will start tracking your left hand to detect a gesture. When you release the pinch, Mivry will stop the tracking and try to identify the gesture you just performed. You can set this to "Manual" to control the start and end of a gesture motion via script by setting the "Left Gesture Trigger Value" and "Right Gesture Trigger Value". The "Left/Right Gesture Trigger Threshold" field decides what value (from 0 to 1) will be considered "gesturing" or "not-gesturing".

- "OnGestureCompletion":

Event callback functions to be called when a gesture was performed.

When these properties are set, the MivryQuestHands component will detect the "trigger", track the position of the hands and, upon release of the "trigger" will automatically identify the gesture and call the OnGestureCompletion function with details about the detected gesture.

## 7: How to use the GestureRecognition script (for one-handed gestures):

(1) Place the Plugins/x86\_64/gesturerecognition.dll (Windows) and/or Plugins/Android/arm64-v8a/libgesturerecognition.so (Android / MobileVR / Oculus Quest) files in the /Assets/Plugins/ folder in your unity project and add the GestureRecognition.cs file to your project scripts.

(2) Create a new Gesture recognition object and register the gestures that you want to identify later.

```
GestureRecognition gr = new GestureRecognition();
int myFirstGesture = gr.createGesture("my first gesture");
int mySecondGesture = gr.createGesture("my second gesture");
```

(3) Record a number of samples for each gesture by calling startStroke(), contdStroke() and endStroke() for your registered gestures, each time inputting the headset and controller transformation.

```
Vector3 hmd_p = Camera.main.gameObject.transform.position;
Quaternion hmd_q = Camera.main.gameObject.transform.rotation;
gr.startStroke(hmd_p, hmd_q, myFirstGesture);
[...]
```

```
// repeat the following while performing the gesture with your controller:
Vector3 p = OVRInput.GetLocalControllerPosition(OVRInput.Controller.RTouch);
Quaternion q = OVRInput.GetLocalControllerRotation(OVRInput.Controller.RTouch);
gr.contdStrokeQ(p,q);
// ^ repeat while performing the gesture with your controller.

[...]
```

```
gr.endStroke();
```

Repeat this multiple times for each gesture you want to identify.  
We recommend recording at least 20 samples for each gesture.

(4) Start the training process by calling startTraining().

You can optionally register callback functions to receive updates on the learning progress by calling setTrainingUpdateCallback() and setTrainingFinishCallback().

```
gr.setMaxTrainingTime(10); // Set training time to 10 seconds.
gr.startTraining();
```

You can stop the training process by calling stopTraining().

After training, you can check the gesture identification performance by calling recognitionScore() (a value of 1 means 100% correct recognition).

(5) Now you can identify new gestures performed by the user in the same way as you were recording samples:

```
Vector3 hmd_p = Camera.main.gameObject.transform.position;
Quaternion hmd_q = Camera.main.gameObject.transform.rotation;
gr.startStroke(hmd_p, hmd_q);
[...]
```

```
// repeat the following while performing the gesture with your controller:
Vector3 p = OVRInput.GetLocalControllerPosition(OVRInput.Controller.RTouch);
Quaternion q = OVRInput.GetLocalControllerRotation(OVRInput.Controller.RTouch);
gr.contdStrokeQ(p,q);
// ^ repeat while performing the gesture with your controller.
[...]
```

```
int identifiedGesture = gr.endStroke();
if (identifiedGesture == myFirstGesture) {
    // ...
}
```

(6) More than just getting the most likely candidate which gesture was performed, you can also get the similarity how much the performed motion resembles the identified gesture:

```
double similarity;
int identifiedGesture = gr.endStroke(similarity);
```

This returns a value between 0 and 1, where 0 indicates that the performed gesture is very much unlike the previously recorded gestures, and 1 indicates that performed gesture is the exact average of all previously recorded gestures and thus highly similar to the intended gesture.

(7) You can save and load your gestures to a gesture database file.

```
gr.saveToFile("C:/myGestures.dat");
// ...
gr.loadFromFile("C:/myGestures.dat");
```

## 8: How to use the GestureCombinations script (for two-handed gestures or gesture combos):

(1) Place the Plugins/x86\_64/gesturerecognition.dll (Windows) and/or Plugins/Android/libgesturerecognition.so (Android / MobileVR / Oculus Quest) files in the /Assets/Plugins/ folder in your unity project and add the GestureCombinations.cs file to your project scripts.

(2) Create a new Gesture recognition object and register the gestures that you want to identify later. (In this example, we use gesture part "0" to mean "left hand" and gesture part "1" to mean right hand, but it could also be two sequential gesture parts performed with the same hand.)

```
GestureCombinations gc = new GestureCombinations(2);
int myFirstCombo = gc.createGestureCombination("wave your hands");
int mySecondCombo = gc.createGestureCombination("play air-guitar");
```

Also, create the individual gestures that each combo will consist.

```
int myFirstCombo_leftHandGesture = gc.createGesture(0, "Wave left hand");
int myFirstCombo_rightHandGesture = gc.createGesture(1, "Wave right hand");
int mySecondCombo_leftHandGesture = gc.createGesture(0, "Hold guitar neck");
int mySecondCombo_rightHandGesture = gc.createGesture(1, "Hit strings");
```

Then set the Gesture Combinations to be the connection of those gestures.

```
gc.setCombinationPartGesture(myFirstCombo, 0, myFirstCombo_leftHandGesture);
gc.setCombinationPartGesture(myFirstCombo, 1, myFirstCombo_rightHandGesture);
gc.setCombinationPartGesture(mySecondCombo, 0, mySecondCombo_leftHandGesture);
gc.setCombinationPartGesture(mySecondCombo, 1, mySecondCombo_rightHandGesture);
```

(3) Record a number of samples for each gesture by calling startStroke(), contdStroke() and endStroke() for your registered gestures, each time inputting the headset and controller transformation.

```
Vector3 hmd_p = Camera.main.gameObject.transform.position;
Quaternion hmd_q = Camera.main.gameObject.transform.rotation;
gc.startStroke(0, hmd_p, hmd_q, myFirstCombo_leftHandGesture);
gc.startStroke(1, hmd_p, hmd_q, myFirstCombo_rightHandGesture);
[...]
// repeat the following while performing the gesture with your controller:
Vector3 p_left = OVRInput.GetLocalControllerPosition(OVRInput.Controller.LTouch);
Quaternion q_left = OVRInput.GetLocalControllerRotation(OVRInput.Controller.LTouch);
gc.contdStrokeQ(0, p_left, q_left);
Vector3 p_right = OVRInput.GetLocalControllerPosition(OVRInput.Controller.RTouch);
Quaternion q_right = OVRInput.GetLocalControllerRotation(OVRInput.Controller.RTouch);
gc.contdStrokeQ(1, p_right, q_right);
// ^ repeat while performing the gesture with your controller.
[...]
gc.endStroke(0);
gc.endStroke(1);
```

Repeat this multiple times for each gesture you want to identify.

We recommend recording at least 20 samples for each gesture, and have different people perform each gesture.

(4) Start the training process by calling `startTraining()`.

You can optionally register callback functions to receive updates on the learning progress by calling `setTrainingUpdateCallback()` and `setTrainingFinishCallback()`.

```
gc.setMaxTrainingTime(60); // Set training time to 60 seconds.
gc.startTraining();
```

You can stop the training process by calling `stopTraining()`. After training, you can check the gesture identification performance by calling `recognitionScore()` (a value of 1 means 100% correct recognition).

(5) Now you can identify new gestures performed by the user in the same way as you were recording samples:

```
Vector3 hmd_p = Camera.main.gameObject.transform.position;
Quaternion hmd_q = Camera.main.gameObject.transform.rotation;
gc.startStroke(0, hmd_p, hmd_q);
gc.startStroke(1, hmd_p, hmd_q);
[...]
```

```
// repeat the following while performing the gesture with your controller:
Vector3 p_left = OVRInput.GetLocalControllerPosition(OVRInput.Controller.LTouch);
Quaternion q_left = OVRInput.GetLocalControllerRotation(OVRInput.Controller.LTouch);
gc.contdStrokeQ(0, p_left, q_left);
Vector3 p_right = OVRInput.GetLocalControllerPosition(OVRInput.Controller.RTouch);
Quaternion q_right = OVRInput.GetLocalControllerRotation(OVRInput.Controller.RTouch);
gc.contdStrokeQ(1, p_right, q_right);
// ^ repeat while performing the gesture with your controller.
[...]
```

```
gc.endStroke(0);
gc.endStroke(1);
int identifiedGestureCombo = gc.identifyGestureCombination();
if (identifiedGestureCombo == myFirstCombo) {
    // ...
}
```

(6) Now you can save and load the artificial intelligence.

```
gc.saveToFile("C:/myGestureCombos.dat");
// ...
gc.loadFromFile("C:/myGestureCombos.dat");
```



## 9: How to use MiVRy with Bolt visual programming graphs

This guide assumes that you have both MiVRy and Bolt already added to your project. You can get both MiVRy and Bolt on the Unity Asset store.

(1) Make sure both Bolt and MiVRy are installed in your project.

Open the **MivryQuestHands.cs** file in the *Assets/GestureRecognition/* folder and un-comment the following line by removing the “//” at the beginning of the line.

```
// #define MIVRY_USE_BOLT
```

to

```
#define MIVRY_USE_BOLT
```

(2) In Unity, open the **Bolt Unit Options Wizard** (in the title bar menu *Tools -> Bolt -> Unit Options Wizard*, if the menu does not exist, check if Bolt was installed properly in your project).


In the Wizard, click “Next” to get to the “Type Options” page.

At the bottom of the list, click the “+” icon twice to add two more entries.

For the two entries select “**MivryQuestHands**” (C# script) and “**Gesture Completion Data**” (object).

Then, click “**Generate**”.

ic & Linux Standalone - Unity 2020.3.16f1 Personal <DX11>



(3) Add the “**MivryQuestHands**” script component to any game object in your scene. (For example, you can right-click in the Hierarchy and select “Create Empty”, select the new object, and in the Inspector click on “Add Component” and choose “MivryQuestHands”.

In the inspector, fill in the values of the MivryQuestHands script components, especially “Gesture Database File”, “Left Hand”, “Left Hand Trigger”, “Right Hand” and “Right Hand Trigger”.

*Alternatively, you could also create a scene variable or graph variable, but then you have to set the member variables (such as “Gesture Database File”) in a Flow Graph instead of just using the Inspector.*


(4) Open your **Bolt flow machine / flow graph** or **state machine / state graph**.

(If you do not yet have a flow graph, you can create one on the same game object by clicking “Add Component” in the Inspector and selecting “Flow Machine”. On the new component click “Edit Graph”).

(5) In the **Variables “Blackboard”**, switch to the “Scene” tab and create a new variable by typing in a Name in the “(New Variable Name)” field and pressing the “+” icon.

If you cannot see the Blackboard, you can open it from the title bar menu “Window” -> “Variables”.

As “**Variable Type**” select “MivryQuestHands”, and as “**Value**” select the object to which you attached the MivryQuestHands script component in step (3).



(6) In the Flow Graph, add a “**Get Scene Variable**” node (by right-clicking in the graph and selecting “Get Scene Variable”), and set it to the MivryQuestHands Variable created in step (5).


Then create a “**Custom Event**” node (right-click in the graph and select “Custom Event”), and connect the Get Variable node as it’s input object.

Change the number of “**Arguments**” to “1”,

and change the **Event** String to the name of your gesture.

This event will now be triggered when the user performed the gesture. You can use this event to trigger further changes in your own code or trigger a transition in a Bolt state machine.

Optionally, you can expose the argument “**Arg. 0**” as “*Gesture Completion Data*”, for example to check the similarity of the gesture performance. (When you expose the object, be sure to select “Instance” and not “Static”).



## 10: Build instructions for Windows

(1) Make sure plug-in file (Plugins/x86\_64/gesturerecognition.dll) is in the “Plugins” folder of your project

(2) In your Unity editor, select the plug-in file and in the inspector make sure it is selected as a plug-in file for the Windows platform.

(3) Place your gesture database (“.DAT”) files in a folder called “StreamingAssets” in your Unity project.

(4) In your Unity script file, use `Application.streamingAssetsPath` as base folder when loading the gesture library instead of an absolute file path. You can use the `UNITY_EDITOR` preprocessor variable to make sure your game will find the gesture recognition database file both when playing in the Unity editor and when building / exporting as a stand-alone game:

```
#if UNITY_EDITOR
gr.loadFromFile("myProject/myGestureDatabaseFile.dat");
#else
gr.loadFromFile(Application.streamingAssetsPath + "/myGestureDatabaseFile.dat");
#endif
```

## 11: Build instructions for Android (Mobile VR, Oculus Quest, ...)

- (1) Make sure plug-in files (Plugins/Android/arm64-v8a/libgesturerecognition.so and Plugins/Android/armeabi-v7a/libgesturerecognition.so) are in the “Plugins” folder of your project.
- (2) In your Unity editor, select the plug-in files and in the inspector make sure it is selected as a plug-in file for the Android platform for ARM64 and ARMv7 respectively.
- (3) Place your gesture database (“.DAT”) files in a folder called “StreamingAssets” in your Unity project.
- (4) In your Unity script file, use Unity’s Android Java API to get the location of the cache folder and use a UnityWebRequest to extract the gesture database file from the .apk to the cache folder and load it from there. This is necessary, because on Android all project files are packed inside the .apk file and cannot be accessed directly. You can use the UNITY\_ANDROID preprocessor variable to make sure your game will find the gesture recognition database file both when playing in the Unity editor and when building / exporting as a stand-alone Android app:

```
LoadGesturesFile = "myGestures.dat";
// Find the location for the gesture database (.dat) file
#ifdef UNITY_EDITOR
// When running the scene inside the Unity editor,
// we can just load the file from the Assets/ folder:
string gesture_file_path = "Assets/GestureRecognition";
#elif UNITY_ANDROID
// On android, the file is in the .apk,
// so we need to first "download" it to the apps' cache folder.
AndroidJavaClass unityPlayer = new AndroidJavaClass("com.unity3d.player.UnityPlayer");
AndroidJavaObject activity = unityPlayer.GetStatic<AndroidJavaObject>("currentActivity");
string gesture_file_path = activity.Call
    <AndroidJavaObject>("getCacheDir").Call<string>("getCanonicalPath");
UnityWebRequest request = UnityWebRequest.Get(Application.streamingAssetsPath
    + "/" + LoadGesturesFile);
request.SendWebRequest();
while (!request.isDone) {
    // wait for file extraction to finish
}
if (request.isNetworkError)
{
    // Failed to extract sample gesture database file from apk
    return;
}
File.WriteAllBytes(gesture_file_path + "/" + LoadGesturesFile, request.downloadHandler.data);
#else
// This will be the case when exporting a stand-alone PC app.
// In this case, we can load the gesture database file from the streamingAssets folder.
string gesture_file_path = Application.streamingAssetsPath;
#endif
if (gr.loadFromFile(gesture_file_path + "/" + LoadGesturesFile) != 0)
{
    // Failed to load sample gesture database file
    return;
}
```

(5) In your project settings, make sure that your settings comply with the Oculus Quest requirements and best practices described at

<https://developer.oculus.com/documentation/unity/unity-conf-settings/>

(6) If you are building for the Quest 2, make sure to set the Color Space in the project settings android section to “Gamma”.

## 12 Troubleshooting and Frequently Asked Questions (FAQ):

- (1) Where in my own program do I have to create the GestureRecognition or GestureCombination object?

*You can create the gesture recognition object anywhere in your project. There are no special requirements where to do it. Commonly, it is created in the XR rig or Oculus/HTC Vive VR framework where the controller input is processed, but this is just one option.*

- (2) How can I get the position of VR controllers (Oculus Touch, HTC Vive Controllers, Valve Knuckles controller etc)?

*As you can see in the Sample\_OneHanded.unity scene, you can use the generic Unity XR rig with two objects "Left Hand" and "Right Hand" which are set to be Generic XR Controllers. So they work for any supported VR device.  
Then, in the C# script you can just use*

```
GameObject left_hand = GameObject.Find("Left Hand");  
gc.contdStroke(Side_Left, left_hand.transform.position, left_hand.transform.rotation);
```

*or*

```
GameObject right_hand = GameObject.Find("Right Hand");  
gc.contdStroke(Side_Right, right_hand.transform.position, right_hand.transform.rotation);
```

- (3) How can I save my own recorded gestures to use them the next time I start Unity?

In your own script, you can save your recorded gestures with

```
gr.saveToFile("C:/where/you/want/your/myGestureCombos.dat");
```

This file you can then load next time you start the program.

If you used the GestureRecognitionSample\_OneHanded Unity file, then your gestures will be saved in your asset folder in

```
GestureRecognition\Sample_TwoHanded_MyRecordedGestures.dat
```

Please see the GestureRecognitionSample\_OneHanded.cs script on line 429 to see how it works.

- (4) How can I open and edit gesture database (.DAT) files?

*Please use the "GestureManager" scene in the Unity sample to open and edit.DAT gesture database files.*

- (5) The Gesture Recognition library does not detect if a gesture is different from all recorded gestures. I want to know if the user makes the gesture I recorded or not.

*The gesture recognition plug-in will always return the number of which other (known)*

*gesture is most similar to the one you just performed.*

*If you want to check if the gesture you made is different from all the recorded gestures, use the following code instead of the normal “endStroke()” function:*

```
double similarity;  
int identified_gesture = endStroke(ref similarity);
```

*Then the similarity variable will give you a measurement of how similar the performed gesture was to the detected gesture. A value of one will indicate perfect similarity, a low value close to zero indicate great differences between the performed gesture and the recorded gesture. You can use this value to judge if the performed gesture is sufficiently similar to the recorded one.*

- (6) Do I have to call “startTraining()” every time I start my game? Does it have to keep running in the background while my app is running?

*No, you only need to call startTraining() after you have recorded new gesture data (samples) and want these new recordings to be used by the AI. However, you need to save the AI after training to a database file (.DAT) and load this file in your game before using the other gesture recognition functions.*

*While the training is running, you cannot use any of the other functions, so you cannot let training run in the background. You must start (and stop) training in between using the AI.*

- (7) How long should I let the training run to achieve optimal recognition performance?

*Usually, the AI will reach its peak performance within one minute of training, but if you’re using a large number of gestures and samples, it may take longer. You can check the current recognition performance from the training callback functions and see if the performance still keeps increasing. If not, feel free to stop the training.*

- (8) Gestures aren’t recognized correctly when I look up/down/left/right or tilt my head.

*You can choose if the frame of reference for your gestures are the players point of view (“head”) or the real world or game world (“world”). For example, if the player is looking up to the sky when performing a gesture towards the sky, then from a “world” frame-of-reference the direction is “up”, but from players “head” point-of-view, the direction is “forward”. Therefore, if you consider your gestures to be relative to the world “up” (sky) and “down” (ground) rather than the visual “upper end of the screen” and “lower end of the screen”, then change the **frameOfReferenceUpDownPitch** to **FrameOfReference.World**. The same setting is available for the yaw (compass direction) and head tilt.*




(9) I'm getting errors about using the Unity "Input" functions (such as GetAxis()).

*In the Unity Project Settings in the "Player" category under "Other", please set "Active Input Handling" from "Input System Package" to "Both".*


(10) I see the VR mirror window on the desktop, but not in the VR headset.

*This can happen if you're using the Unity "OpenXR Plugin" for VR (as the GestureManager and Samples do). In this case, please make sure that OpenXR is enabled in your VR app's settings:*

*Oculus App:*



*SteamVR:*



(11) What is the "Update Head Position Policy" / "Compensate Head Motion" setting?

This setting decides whether the AI should consider changes in head position during the gesturing. During gesturing, the current position of the VR headset can/will be updated via the "updateHeadPosition" procedure. This data is saved together with the motion data.

However, in many cases it is not advisable to take head motions during gesturing into account, because people may watch their hands while gesturing. Following the moving hands with the head would then eliminate the hand motion relative to the headset (the hands would always be "in front of the headset").

However, in some cases it may be useful to use the changing head position, for example if the user might be walking during a gesture. You can choose whether or not the data provided via calls to "updateHeadPosition" functions will be used with the UpdateHeadPositionPolicy (or call to GestureRecognition.setUpdateHeadPositionPolicy()). "UseLatest" will cause MiVRy to use the changing head position, thus compensating the relative head motion during gesturing.

"UseInitial" will not consider changes in head motion during gesturing, but only the head position at the start of the gesture. Note that if you use a GestureRecognition or GestureCombinations object directly, you also need to provide the changing head position via "updateHeadPosition()" for this to have any effect. Also note that the data provided via "updateHeadPosition" is stored regardless of the policy, even when it is not used later.

(12) MiVRy identifies any motion as some gesture, even when it doesn't resemble any of the recorded gestures. Why? How can I tell if no valid gesture motion was performed?

A: MiVRy will always tell you the "most likely" best guess as to which gesture was just performed, no matter how different the currently performed motion is from all recorded gestures. This is because we cannot decide for you how much difference is tolerable.

In order to disqualify "wrong" motions, you have two options:

(A) you can check the "similarity" value returned by MiVRy. This value describes how similar the gesture motion was compared to previous recordings on a scale from 0 (very different) to 1 (very similar).

(B) you can check the "probability" value. Especially when you compare the probability values for all recorded gestures (for example via the "endStrokeAndGetAllProbabilitiesAndSimilarities" function) and see that they are all very low and not very different from one another, you may want to decide that the current gesture performance was not valid.

- (13) What exactly does the "similarity" value of a gesture performance mean? How is it different from the probability value?

The "similarity" value expresses how much the identified gesture differs from the average of the recorded samples for that gesture. When you record several samples, MiVRy internally calculates a "mean" ("average", "typical") gesture motion based on those samples. It also calculates how much the recorded samples differ from this "mean" (ie. the "variance" of the samples). The "similarity" value is then calculated based on this "mean". If your newly performed gesture motion hits exactly this "average", then the similarity value will be one. The more it differs, the lower the "similarity" value will be, going towards zero. How fast it will fall depends on how similar the recorded samples were. If all recorded samples looked exactly the same, then MiVRy will be very strict, and the "similarity" value will fall fast when the currently performed motion isn't also exactly alike. If, however the samples differed a lot, MiVRy will be more tolerant when calculating the "similarity" value and it will be higher. The value is always between 0 and 1. This "similarity" is different from the "probability" values, which are estimates by the artificial intelligence (neural network). "Probability" may contain many more considerations, for example if there are other gestures who resemble the identified gesture (probability may drop, similarity is unaffected), or if there are a multitude of distinct motions lumped together as one "gesture" (for example: having a gesture "alphabet" which contains drawings of "A", "B", "C" etc all lumped together as one gesture - then "similarity" will be calculated based on an "average" character that doesn't resemble any sample, but the AI may successfully understand what you mean and give high "probability" values).

- (14) Instead of triggering the start and end of a gesture motion, I want MiVRy to constantly run in the background and detect gestures as they occur.

You can use the "Continuous Gesture Identification" feature of MiVRy. When using the "GestureRecognition" or "GestureCombinations" objects directly, use the "contdIdentify" function - you can call this function repeatedly (for example on every frame) and every time it will tell you which gesture is currently being performed. When using the "Mivry" component, use the "Continuous Gesture Identification" switch. Either way, two settings are important for Continuous Gesture Identification: "Continuous Gesture Period" and "Continuous Gesture Smoothing". "Continuous Gesture Period" is the time frame (in milliseconds) that continuous gestures are expected to be. So, if your gestures take 1 second to perform, set this to "1000" so that MiVRy will consider the last 1000 ms to identify the gesture. "Continuous Gesture Smoothing" is the number of samples (previous calls to "contdIdentify" to use for smoothing continuous gesture identification results). When setting this to zero, each attempt to identify the gesture will stand alone. If ContinuousGestureSmoothing is higher than zero, MiVRy will remember previous attempts to identify the gesture and will produce more stable output.

(15) After some time, all attempts to identify a gesture fail with error code -16.

*You have used up all “free” gesture recognitions of the free version of MiVRy for this session. To identify more gestures, restart the app, or purchase an “unlimited” license at <https://www.marui-plugin.com/mivry/>*

### 13 Software license statement (EULA):

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

[IMPORTANT!] This license is for the gesture recognition plug-in (.dll and .so files and source code) and does NOT include any permission to use the asset and resource files used in the samples (3D models and textures etc.)